

by *kate SPAIN*  
**Verna**  
 quilt and bag pattern

Quilt Size: 42"x42"  
 Bag Size: Approx. 19"x20"

**Yardage Requirements:**



1 – Charm Pack #27000PP

Sashing #27012-14      ½ yard

Final Border #27008-14      ¾ yard

Binding #27007-13      ½ yard

Backing                      1½ yards



Bag Front #27001-11      1½ yards

Lining, Straps & Tie #27008-11

1½ yards

**EXTRAS**

*Pellon Thermolam Plus*      ¾ yard

1" wide Cotton Belting      4 yards

*505 Fabric Spray*



Please note, kit yardage may vary slightly from amounts given on this project sheet.

*Pattern for Quilt and Bag*



*moda*

MODAFABRICS.COM

PS27000— SUGGESTED RETAIL \$6.00

by *kate SPAIN*  
**Verna**  
*moda*

# Verna

by kate SPAIN

Quilt Size: 42"x42"

## Quilter Basics

*Read instructions before beginning a project.*

*All instructions include a 1/4" seam allowance.*

*Press as you go. Press seams in one direction.*

## Cutting

### QUILT

#### Sashing

6-2 1/2" x WOF

subcut 2-2 1/2" x 14"  
3-2 1/2" x 29 1/2"  
2-2 1/2" x 33 1/2"

#### Final Border

4-5" x WOF

subcut 2-5" x 33 1/2"  
2-5" x 42 1/2"

#### Binding

5-2 1/2" x WOF

### BAG

#### Bag Front

1-20 1/2" x 37 1/2" (front)  
1-15" x 16 1/2" (sleeve)

#### Bag Lining


1-20 1/2" x 41 1/2" (front)  
3-3" x WOF (strap)  
1-6" x WOF (tie)

Pellon 1-20 1/2" x 37 1/2"

*moda*


## Quilt Construction

- Combine 3-5"x5" squares in a row. Join the rows to make a Nine Square block. Make four Nine Square blocks.




Nine Square Block  
Make 4  
14"x14" with seams

- Sew two Nine Square Blocks and 1-2 1/2" x 14" Sashing strip together. See diagram. Make 2.



Make 2  
14"x29 1/2" with seams

- Add the Sashing and the Final Border in the order shown. Sew the 5-2 1/2" x WOF binding strips together using a bias seam. Layer, quilt and bind the quilt. ENJOY!




*moda*






by **kate SPAIN**  
**Verna** bag construction


**1 Mark the Bag Front:** Using a water soluble pen, mark the lines on the Bag Front. See the blue lines on diagram (A). Use the 505 Spray to secure the Thermolam to the back of the Bag Front.




**2 Add the Lining:** Mark the centers of the Lining. Pin the ends of the Bag Front and Lining, right sides together. Stitch. Align the center of the Bag Front and the Lining. Pin. (The Lining will extend 1" past the Bag Front since the Bag Front is shorter than the lining.) Press. Sew the sides, leaving an opening in one side. Clip the corners. Turn right side out through the opening. Press. Stitch the opening closed. Topstitch an 1/8" below the lining.




**3 Make the Bag Sleeve:** (A) Press the edges of the Sleeve in 1/2", wrong sides together. Open. (B) Sew the long edge, right sides together. (C) Press the 1/2" edges back into position. Turn right side out and press, centering the seam on the back. Topstitch 1/8" and 1/4" from the edge.




**4 Sew Bag Sleeve to the Bag:** Align the sides of the Bag Sleeve to the blue lines and center on the Bag. Topstitch 1/8" and 1/4" from the sides ONLY.



**5 To make and attach the straps:** Sew the 3-3" x WOF strips end to end to form one long strip. Fold the long edges of the strips under 1/4" on both sides. Press. Open the pressing on the ends, sew the ends wrong sides together, to make one continuous loop. Place the 1" cotton belting inside the strap under one of the 1/4" edges. Trim to size. Spray the cotton belting with 505 Spray, fold the edges together to cover the belting. Edgestitch along both of the long edges; then sew a line of stitching down the middle of the strap.





6 Stitch the strap to the Bag Front. See diagram. Only stitch where the black dash lines are shown in the diagram.




7 Fold the Bag in half, right sides together. Draw a line 2½" from the top of Bag. Start stitching at this line, down the side of the Bag. Repeat on the other side.

8 Pinch the bottom of the Bag. Measure 2½" from points. Stitch both ends. Trim ¼" from the stitching.



9 Make the Tie: Fold the 6" x WOF Tie in half right sides together. Stitch the ends and the side, leaving an opening. Clip the corners. Turn right side out through the opening. Press. Stitch the opening closed. Thread the Tie through the strap openings.



Fold the quilt in half and roll tightly. Stow in the bottom sleeve.

